

CONFIDENTIAL

ADSP Reference Renderer/Capture Plugin RCG3AHPLN0203ZDO

User's Manual

RCG3AHPLN0203ZDOE

All information contained in these materials, including products and product specifications, represents information on the product at the time of publication and is subject to change by Renesas Electronics Corp. without notice. Please review the latest information published by Renesas Electronics Corp. through various means, including the Renesas Electronics Corp. website (<http://www.renesas.com>).

Rev. 1.00 May, 2019

CONFIDENTIAL

Notice

1. Descriptions of circuits, software and other related information in this document are provided only to illustrate the operation of semiconductor products and application examples. You are fully responsible for the incorporation or any other use of the circuits, software, and information in the design of your product or system. Renesas Electronics disclaims any and all liability for any losses and damages incurred by you or third parties arising from the use of these circuits, software, or information.
 2. Renesas Electronics hereby expressly disclaims any warranties against and liability for infringement or any other claims involving patents, copyrights, or other intellectual property rights of third parties, by or arising from the use of Renesas Electronics products or technical information described in this document, including but not limited to, the product data, drawings, charts, programs, algorithms, and application examples.
 3. No license, express, implied or otherwise, is granted hereby under any patents, copyrights or other intellectual property rights of Renesas Electronics or others.
 4. You shall not alter, modify, copy, or reverse engineer any Renesas Electronics product, whether in whole or in part. Renesas Electronics disclaims any and all liability for any losses or damages incurred by you or third parties arising from such alteration, modification, copying or reverse engineering.
 5. Renesas Electronics products are classified according to the following two quality grades: "Standard" and "High Quality". The intended applications for each Renesas Electronics product depends on the product's quality grade, as indicated below.
"Standard": Computers; office equipment; communications equipment; test and measurement equipment; audio and visual equipment; home electronic appliances; machine tools; personal electronic equipment; industrial robots; etc.
"High Quality": Transportation equipment (automobiles, trains, ships, etc.); traffic control (traffic lights); large-scale communication equipment; key financial terminal systems; safety control equipment; etc.
Unless expressly designated as a high reliability product or a product for harsh environments in a Renesas Electronics data sheet or other Renesas Electronics document, Renesas Electronics products are not intended or authorized for use in products or systems that may pose a direct threat to human life or bodily injury (artificial life support devices or systems; surgical implantations; etc.), or may cause serious property damage (space system; undersea repeaters; nuclear power control systems; aircraft control systems; key plant systems; military equipment; etc.). Renesas Electronics disclaims any and all liability for any damages or losses incurred by you or any third parties arising from the use of any Renesas Electronics product that is inconsistent with any Renesas Electronics data sheet, user's manual or other Renesas Electronics document.
 6. When using Renesas Electronics products, refer to the latest product information (data sheets, user's manuals, application notes, "General Notes for Handling and Using Semiconductor Devices" in the reliability handbook, etc.), and ensure that usage conditions are within the ranges specified by Renesas Electronics with respect to maximum ratings, operating power supply voltage range, heat dissipation characteristics, installation, etc. Renesas Electronics disclaims any and all liability for any malfunctions, failure or accident arising out of the use of Renesas Electronics products outside of such specified ranges.
 7. Although Renesas Electronics endeavors to improve the quality and reliability of Renesas Electronics products, semiconductor products have specific characteristics, such as the occurrence of failure at a certain rate and malfunctions under certain use conditions. Unless designated as a high reliability product or a product for harsh environments in a Renesas Electronics data sheet or other Renesas Electronics document, Renesas Electronics products are not subject to radiation resistance design. You are responsible for implementing safety measures to guard against the possibility of bodily injury, injury or damage caused by fire, and/or danger to the public in the event of a failure or malfunction of Renesas Electronics products, such as safety design for hardware and software, including but not limited to redundancy, fire control and malfunction prevention, appropriate treatment for aging degradation or any other appropriate measures. Because the evaluation of microcomputer software alone is very difficult and impractical, you are responsible for evaluating the safety of the final products or systems manufactured by you.
 8. Please contact a Renesas Electronics sales office for details as to environmental matters such as the environmental compatibility of each Renesas Electronics product. You are responsible for carefully and sufficiently investigating applicable laws and regulations that regulate the inclusion or use of controlled substances, including without limitation, the EU RoHS Directive, and using Renesas Electronics products in compliance with all these applicable laws and regulations. Renesas Electronics disclaims any and all liability for damages or losses occurring as a result of your noncompliance with applicable laws and regulations.
 9. Renesas Electronics products and technologies shall not be used for or incorporated into any products or systems whose manufacture, use, or sale is prohibited under any applicable domestic or foreign laws or regulations. You shall comply with any applicable export control laws and regulations promulgated and administered by the governments of any countries asserting jurisdiction over the parties or transactions.
 10. It is the responsibility of the buyer or distributor of Renesas Electronics products, or any other party who distributes, disposes of, or otherwise sells or transfers the product to a third party, to notify such third party in advance of the contents and conditions set forth in this document.
 11. This document shall not be reprinted, reproduced or duplicated in any form, in whole or in part, without prior written consent of Renesas Electronics.
 12. Please contact a Renesas Electronics sales office if you have any questions regarding the information contained in this document or Renesas Electronics products.
- (Note 1) "Renesas Electronics" as used in this document means Renesas Electronics Corporation and also includes its directly or indirectly controlled subsidiaries.
- (Note 2) "Renesas Electronics product(s)" means any product developed or manufactured by or for Renesas Electronics.

CONFIDENTIAL

Trademarks

- Linux® is the registered trademark of Linus Torvalds in the U.S. and other countries.
- Android™ is a trademark of Google LLC. Use of this trademark is subject to Google Permissions.
- Arm is a registered trademark of Arm Limited (or its subsidiaries) in the US and/or elsewhere.
- Windows and Windows Media are registered trademarks of Microsoft Corporation in the United States and other countries.
- Android is a trademark of Google Inc. Use of this trademark is subject to Google permissions.
- All other company names and product names mentioned in this manual are registered trademarks or trademarks of their respective companies.
- The registered trademark symbol (®) and trademark symbol (™) are omitted in this manual.

How to Use This Manual

1. Purpose and Target Reader

This manual is designed to provide the user with an understanding of the interface specifications of the Software product. It is intended for users designing application systems incorporating the Software product. Please refer to the related documents with this product.

Use this Software after carefully reading the precautions. The precautions are stated in the main text of each section, at the end of each section, and in the usage precaution section.

The revision history summarizes major corrections and additions to the previous version. It does not cover all the changes. For details, refer to this manual.

2. Restrictions on the Use of this Software

This software is MIT license. The certificates from the licensor do not provide any assurances to users that the product performs reliably, intellectual property rights are protected, disputes are resolved by contract, and specifications are not subject to major changes. The user should use this software at his or her own risk.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

3. Related Manuals

4. Technical Terms and Abbreviation

- Table of Contents -

1. OVERVIEW	3
1.1 Specifications Outline	3
1.2 Configuration	5
2. SOFTWARE SPECIFICATIONS	9
2.1 API specifications	9
2.2 Command	10
2.2.1 Command list	11
2.2.2 Detail of Command Specifications	21
2.3 Structures	94
2.3.1 XARelldr type structure	95
2.3.2 XARelcap type structure	97
2.4 Memory Specifications	98
2.4.1 Persistent Area	98
2.4.2 Stack Area	99
2.4.3 Heap Area	99
2.4.4 Input Buffer	100
2.4.5 Output Buffer	100
2.5 Error Processing	102
2.5.1 Error codes	102
3. PROCESSING FLOW	109
4. APPENDIX	111
4.1 CTU (Channel transfer unit)	111
4.2 MIX (Mixing)	112
4.3 16-bit monaural	114
4.4 Conversion functions	114
4.5 State transformation	115

- List of Figures -

Figure 1-1	Example of the ADSP System Configuration for renderer function	5
Figure 1-2	Example of the ADSP System Configuration uses CTU/MIX for renderer function	6
Figure 1-3	Example of the ADSP System Configuration for capture function	7
Figure 2-1	Command sequence overview	10
Figure 2-2	PCM 16-bit Data Access (Little Endian Mode)	101
Figure 2-3	PCM 24-bit Data Access (Little Endian Mode)	101
Figure 2-4	Output Formats	101
Figure 3-1	Example of the Application Processing Flow	110
Figure 4-1	Block diagram of CTU	111
Figure 4-2	Example of using CTU/MIX for 3 streams to SSI0 and another stream to SSI3	112
Figure 4-3	Example of using CTU/MIX to play 8 streams to SSI0 and SSI3	113
Figure 4-4	Data format of 16-bit monaural in SW and HW	114
Figure 4-5	State transformation in the plugin	115

- List of Tables -

Table 1-1	Basic Specification	3
Table 1-2	Supported Specifications for capture function	3
Table 1-3	Supported Specifications for renderer function.....	3
Table 1-4	Memory Size Requirements	4
Table 1-5	Version Information	4
Table 2-1	API Functions of renderer	9
Table 2-2	API Functions of capture	9
Table 2-3	List of supported none supported command, subcommand	11
Table 2-4	List of Initialization Commands.....	13
Table 2-5	List of Set Commands for renderer.....	14
Table 2-6	List of Set Commands for capture	15
Table 2-7	List of Memory allocation Commands.....	16
Table 2-8	List of initialize commands	17
Table 2-9	List of Get commands for renderer	18
Table 2-10	List of Get commands for capture	19
Table 2-11	List of execution commands	20
Table 2-12	Structures.....	94
Table 2-13	XARelrdr type structure information	96
Table 2-14	XARelcap type structure information.....	97
Table 2-15	Persistent Area Description.....	98
Table 2-16	Stack Area Description.....	99
Table 2-17	Input Buffer Description.....	100
Table 2-18	Output Buffer Description.....	100
Table 2-19	Error Codes for Renderer	102
Table 2-20	Error Codes for Capture	106

1. Overview

This section provides an overview of the Renderer plugin. It contains renderer and capture function.

1.1 Specifications Outline

Renderer function plays the audio signal based on the parameter that was set.

Capture function capture/record the audio signal based on the parameter that was set.

Table 1-1 Basic Specification

Item	Description
DSP	Cadence Design Systems, Inc. HiFi2
Compiler	Xtensa C and C++ Compiler (version 12.0.4)
Endian	Little Endian

Table 1-2 Supported Specifications for capture function

Item	Description
Input data format	16-bit/24-bit linear PCM (fixed point)
Output data format	16-bit/24-bit linear PCM (fixed point)
Sampling frequency (Hz) supported	48000 / 44100 / 32000
Number of channels supported	Max 2 channels
Reentrant	Supported
Volume control	Support volume update during plugin execution
Other	-
Restrictions	-

Table 1-3 Supported Specifications for renderer function

Item	Description
Input data format	16-bit/24-bit linear PCM (fixed point)
Output data format	16-bit/24-bit linear PCM (fixed point)
Sampling frequency (Hz) supported	48000 / 44100 / 32000
Input data channel	Monaural, stereo, 4 channels, 6 channels, 8 channels
Output data channel	Max 2 channels
Reentrant	Supported
Volume control	Support volume update during plugin execution.
Other	-
Restrictions	-

[Note] In case of channel transfer from input monaural to output stereo, the sound will output to both two channels.

Table 1-4 Memory Size Requirements

Memory type	Location	Memory area name		Size (in bytes)	
Instruction	ROM	Instruction area		78393	
Data		Constant table area			
		Other area(Depended on the compiler)			
	Software work area		1756		
	Area breakdown	Persistent area	Size breakdown	1692	
		Scratch area		0	
		Built-in descriptor area		64	
	User work area		9576		
	Area breakdown	Input buffer	Size breakdown	0	
		Output buffer		8192	
		Structure		1384	
	Stack area		1168		
	Other area(Depended on the compiler)		0		
	Software work area		1748		
	Area breakdown	Persistent area	Size breakdown	1684	
Scratch area		0			
Built-in descriptor area		64			
User work area		9616			
Area breakdown	Input buffer	Size breakdown	8192		
	Output buffer		0		
	Structure		1424		
Stack area		1440			
Other area(Depended on the compiler)		0			

[Note] Area whose location is shown as ROM in the location column can be included in RAM or ROM.

[Note] Area whose location is shown as RAM in the location column can be included in RAM only.

[Note] Built-in is a memory area to allocate descriptor memory, which need in the DMAC transfer type of plugin.

Table 1-5 Version Information

Item	Description
Library Version information	Version 1.0.4
API Version information	Version 1.0.0

1.2 Configuration

Figure 1-1 shows an example of the ADSP system configuration which uses renderer function.




Figure 1-1 Example of the ADSP System Configuration for renderer function

Figure 1-2 show an example of using channel converter and mixer function to mix 4 streams from 4 Renderer plugins.




Figure 1-2 Example of the ADSP System Configuration uses CTU/MIX for renderer function

Figure 1-3 shows an example of the ADSP system configuration which uses capture function.




Figure 1-3 Example of the ADSP System Configuration for capture function

1. Stream (Compressed Audio data)
Compressed Audio data is a linear PCM data sample compressed according to the compression Audio specifications. For these specifications, depends on HiFi2 Codec Library.
2. HiFi2 Codec Library
It is Codec Library for HiFi2. It decodes the compression Audio in renderer case and encodes in capture case. The user should procure to suit the target system.
3. ADSP Framework
It controls ADSP Plugin. It is software provided separately as Framework.
4. HiFi2 Renderer (ADSP Reference Plugin)
It performs output handling of PCM data to other Audio device. It is this software set up as ADSP Reference Plugin.
5. HiFi2 Capture (ADSP Reference Plugin)
It performs input handling of PCM data from other Audio device. It is this software set up as ADSP Reference Plugin.
6. PCM data
16-bit/24-bit linear PCM data which is a processing by this software.

7. SCU

It performs sampling rate converters (SRC), channel transfer (CTU), mixing (MIX), and volume control (DVC).

8. SRC

It performs sampling rate conversion function.

9. CTU

It performs channel transfer unit function such as down-mixing and splitter functions.

10. MIX

It is used for mixing (adding) streams from two to four audio stream sources into a single stream. It also support the volume control (gain level) for each input stream.

11. DVC

It performs mute and volume control functions.

12. SSI

Send or receive audio data interfacing with a variety devices of offering I2C format.

13. ADC

The ADC converts an analog signal into 16-bit linear PCM data.

2. Software Specifications

2.1 API specifications

Because one interface function accesses the procedure that was appointed by a command in renderer plugin, it is used.

In renderer case

Table 2-1 API Functions of renderer

xa_rel_rdr	
Description	This API is the only access function to the renderer.
Syntax	XA_ERRORCODE xa_rel_rdr(xa_codec_handle_t p_xa_module_obj, WORD32 i_cmd, WORD32 i_idx, pVOID pv_value);
Parameters	p_xa_module_obj : Pointer to opaque API structure. i_cmd : Command. (defined in the supplied header files as) i_idx : Command subtype or index. (defined in the supplied header files as) pv_value : Pointer to the variable used to pass in, or get out properties, from state structure.
Returns	Error Code based on the success or failure of API command (defined in the supplied header files as)

In capture case

Table 2-2 API Functions of capture

xa_rel_cap	
Description	This API is the only access function to the capture.
Syntax	XA_ERRORCODE xa_rel_cap(xa_codec_handle_t p_xa_module_obj, WORD32 i_cmd, WORD32 i_idx, pVOID pv_value);
Parameters	p_xa_module_obj : Pointer to opaque API structure. i_cmd : Command. (defined in the supplied header files as) i_idx : Command subtype or index. (defined in the supplied header files as) pv_value : Pointer to the variable used to pass in, or get out properties, from state structure.
Returns	Error Code based on the success or failure of API command (defined in the supplied header files as)

2.2 Command

Using API functions of the REF_Ref466909483 ¥h ¥* MERGEFORMAT Table 2-1 and REF_Ref466909488 ¥h ¥* MERGEFORMAT Table 2-2, it performs each processing by a combination of Command/Subcommand.




Figure 2-1 Command sequence overview

2.2.1 Command list

Below table presents commands used in renderer and capture case.

Table 2-3 List of supported none supported command, subcommand

Command	Sub command	Ren	Cap
XA_API_CMD_GET_LIB_ID_STRINGS	XA_CMD_TYPE_LIB_VERSION	Y	Y
	XA_CMD_TYPE_API_VERSION	Y	Y
XA_API_CMD_GET_API_SIZE	-	Y	Y
XA_API_CMD_INIT	XA_CMD_TYPE_INIT_API_PRE_CONFIG_PARAMS	Y	Y
	XA_CMD_TYPE_INIT_API_POST_CONFIG_PARAMS	Y	Y
	XA_CMD_TYPE_INIT_PROCESS	Y	Y
	XA_CMD_TYPE_INIT_DONE_QUERY	Y	Y
XA_API_CMD_SET_CONFIG_PARAM	XA_CAP_CONFIG_PARAM_PCM_WIDTH	N	Y
	XA_CAP_CONFIG_PARAM_CHANNELS	N	Y
	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	N	Y
	XA_CAP_CONFIG_PARAM_FRAME_SIZE	N	Y
	XA_CAP_CONFIG_PARAM_INPUT1	N	Y
	XA_CAP_CONFIG_PARAM_DMACHANNEL1	N	Y
	XA_CAP_CONFIG_PARAM_INPUT2	N	Y
	XA_CAP_CONFIG_PARAM_DMACHANNEL2	N	Y
	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	N	Y
	XA_CAP_CONFIG_PARAM_VOLUME_RATE	N	Y
	XA_CAP_CONFIG_PARAM_STATE	N	Y
	XA_CAP_CONFIG_PARAM_RING_NUM	N	Y
	XA_RDR_CONFIG_PARAM_PCM_WIDTH	Y	N
	XA_RDR_CONFIG_PARAM_CHANNELS	Y	N
	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	Y	N
	XA_RDR_CONFIG_PARAM_FRAME_SIZE	Y	N
	XA_RDR_CONFIG_PARAM_OUTPUT1	Y	N
	XA_RDR_CONFIG_PARAM_DMACHANNEL1	Y	N
	XA_RDR_CONFIG_PARAM_OUTPUT2	Y	N
	XA_RDR_CONFIG_PARAM_DMACHANNEL2	Y	N
	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	Y	N
	XA_RDR_CONFIG_PARAM_VOLUME_RATE	Y	N
	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	Y	N
	XA_RDR_CONFIG_PARAM_MIX_CONTROL	Y	N
	XA_RDR_CONFIG_PARAM_STATE	Y	N
	XA_RDR_CONFIG_PARAM_RING_NUM	Y	N
XA_API_CMD_GET_CONFIG_PARAM	XA_CAP_CONFIG_PARAM_PCM_WIDTH	N	Y
	XA_CAP_CONFIG_PARAM_CHANNELS	N	Y
	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	N	Y
	XA_CAP_CONFIG_PARAM_FRAME_SIZE	N	Y
	XA_CAP_CONFIG_PARAM_INPUT1	N	Y
	XA_CAP_CONFIG_PARAM_DMACHANNEL1	N	Y
	XA_CAP_CONFIG_PARAM_INPUT2	N	Y
	XA_CAP_CONFIG_PARAM_DMACHANNEL2	N	Y
	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	N	Y
	XA_CAP_CONFIG_PARAM_VOLUME_RATE	N	Y
	XA_CAP_CONFIG_PARAM_STATE	N	Y
	XA_CAP_CONFIG_PARAM_RING_NUM	N	Y
	XA_RDR_CONFIG_PARAM_PCM_WIDTH	Y	N
	XA_RDR_CONFIG_PARAM_CHANNELS	Y	N
	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	Y	N
	XA_RDR_CONFIG_PARAM_FRAME_SIZE	Y	N
	XA_RDR_CONFIG_PARAM_OUTPUT1	Y	N
	XA_RDR_CONFIG_PARAM_DMACHANNEL1	Y	N
	XA_RDR_CONFIG_PARAM_OUTPUT2	Y	N

	XA_RDR_CONFIG_PARAM_DMACHANNEL2	Y	N
	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	Y	N
	XA_RDR_CONFIG_PARAM_VOLUME_RATE	Y	N
	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	Y	N
	XA_RDR_CONFIG_PARAM_MIX_CONTROL	Y	N
	XA_RDR_CONFIG_PARAM_STATE	Y	N
	XA_RDR_CONFIG_PARAM_RING_NUM	Y	N
XA_API_CMD_GET_MEMTABS_SIZE	-	Y	Y
XA_API_CMD_SET_MEMTABS_PTR	-	Y	Y
XA_API_CMD_GET_N_MEMTABS	-	Y	Y
XA_API_CMD_GET_MEM_INFO_SIZE	-	Y	Y
XA_API_CMD_GET_MEM_INFO_ALIGNMENT	-	Y	Y
XA_API_CMD_GET_MEM_INFO_TYPE	-	Y	Y
XA_API_CMD_SET_MEM_PTR	-	Y	Y
XA_API_CMD_SET_INPUT_BYTES	-	Y	N
XA_API_CMD_INPUT_OVER	-	N	Y
XA_API_CMD_GET_CURIDX_INPUT_BUF	-	Y	N
XA_API_CMD_EXECUTE	XA_CMD_TYPE_DO_EXECUTE	N	Y
	XA_CMD_TYPE_DONE_QUERY	Y	N
XA_API_CMD_GET_OUTPUT_BYTES	-	N	Y

Ren: Renderer Cap: Capture

Y: command or sub command is used by renderer or capture.

N: command or sub command is not used by renderer or capture. They are presented in detailed command part to refer. Actually, they are not implemented.

-: None sub command

2.2.1.1 Start-up API

Table 2-4 List of Initialization Commands

upper stage: Command / lower step : Subcommand		Description
1	XA_API_CMD_GET_LIB_ID_STRINGS	Get the version of the library
	XA_CMD_TYPE_LIB_VERSION	
2	XA_API_CMD_GET_LIB_ID_STRINGS	Get the version of the API
	XA_CMD_TYPE_API_VERSION	
3	XA_API_CMD_GET_API_SIZE	Get the size of the API structure
	Null	
4	XA_API_CMD_INIT	Set the default values of all the configuration parameters
	XA_CMD_TYPE_INIT_API_PRE_CONFIG_PARAMS	

2.2.1.2 Setting parameters

Table 2-5 List of Set Commands for renderer

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_SET_CONFIG_PARAM	Set the input PCM sample bit width to 16 or 24 bits
	XA_RDR_CONFIG_PARAM_PCM_WIDTH	
2	XA_API_CMD_SET_CONFIG_PARAM	Set the input PCM channels (support monaural, stereo, 4 channels, 6 channels, 8 channels)
	XA_RDR_CONFIG_PARAM_CHANNELS	
3	XA_API_CMD_SET_CONFIG_PARAM	Set the input PCM sampling frequency (supported 32000/44100/48000Hz)
	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	
4	XA_API_CMD_SET_CONFIG_PARAM	Set the input/output frame size
	XA_RDR_CONFIG_PARAM_FRAME_SIZE	
5	XA_API_CMD_SET_CONFIG_PARAM	Set the output destination Audio 1 st device for Renderer
	XA_RDR_CONFIG_PARAM_OUTPUT1	
6	XA_API_CMD_SET_CONFIG_PARAM	Set ADMA channel number usage for Audio device 1 st (supported Audio-DMAC, Audio-DMAC-pp)
	XA_RDR_CONFIG_PARAM_DMACHANNEL1	
7	XA_API_CMD_SET_CONFIG_PARAM	Set the output destination Audio 2 nd device for Renderer
	XA_RDR_CONFIG_PARAM_OUTPUT2	
8	XA_API_CMD_SET_CONFIG_PARAM	Set ADMA channel number usage for Audio device 2 nd (supported Audio-DMAC, Audio-DMAC-pp)
	XA_RDR_CONFIG_PARAM_DMACHANNEL2	
9	XA_API_CMD_SET_CONFIG_PARAM	Set the output PCM sampling frequency (supported 32000/44100/48000Hz)
	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	
10	XA_API_CMD_SET_CONFIG_PARAM	Set the output PCM volume rate compare with input PCM (supported from 0 – 8 times)
	XA_RDR_CONFIG_PARAM_VOLUME_RATE	
11	XA_API_CMD_SET_CONFIG_PARAM	Set the output PCM channels (support maximum 2 channels)
	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	
12	XA_API_CMD_SET_CONFIG_PARAM	Set the MIX module usage for Renderer (value 1/0 to used/unused mix function)
	XA_RDR_CONFIG_PARAM_MIX_CONTROL	
13	XA_API_CMD_SET_CONFIG_PARAM	Set the operation state of Renderer plugin (RUN/PAUSE/IDLE/RESET)
	XA_RDR_CONFIG_PARAM_STATE	
14	XA_API_CMD_SET_CONFIG_PARAM	Set the total number of ring buffers to use
	XA_RDR_CONFIG_PARAM_RING_NUM	

Table 2-6 List of Set Commands for capture

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_SET_CONFIG_PARAM	Set the input PCM sample bit width to 16 or 24 bits
	XA_CAP_CONFIG_PARAM_PCM_WIDTH	
2	XA_API_CMD_SET_CONFIG_PARAM	Set the input PCM channels (Maximum is 2 channels)
	XA_CAP_CONFIG_PARAM_CHANNELS	
3	XA_API_CMD_SET_CONFIG_PARAM	Set the input PCM sampling frequency (supported 32000/44100/48000Hz)
	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	
4	XA_API_CMD_SET_CONFIG_PARAM	Set the input/output frame size
	XA_CAP_CONFIG_PARAM_FRAME_SIZE	
5	XA_API_CMD_SET_CONFIG_PARAM	Set the input source Audio 1 st device for Capture
	XA_CAP_CONFIG_PARAM_INPUT1	
6	XA_API_CMD_SET_CONFIG_PARAM	Set ADMA channel number usage for Audio device 1 st (supported Audio-DMAC, Audio-DMAC-pp)
	XA_CAP_CONFIG_PARAM_DMACHANNEL1	
7	XA_API_CMD_SET_CONFIG_PARAM	Set the input source Audio 2 nd device for Capture
	XA_CAP_CONFIG_PARAM_INPUT2	
8	XA_API_CMD_SET_CONFIG_PARAM	Set ADMA channel number usage for Audio device 2nd (supported Audio-DMAC, Audio-DMAC-pp)
	XA_CAP_CONFIG_PARAM_DMACHANNEL2	
9	XA_API_CMD_SET_CONFIG_PARAM	Set the output PCM sampling frequency (supported 32000/44100/48000Hz)
	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	
10	XA_API_CMD_SET_CONFIG_PARAM	Set the output PCM volume rate compare with input PCM (supported from 0 – 8 times)
	XA_CAP_CONFIG_PARAM_VOLUME_RATE	
11	XA_API_CMD_SET_CONFIG_PARAM	Set the operation state of Capture plugin (RUN/PAUSE/IDLE/RESET)
	XA_CAP_CONFIG_PARAM_STATE	
12	XA_API_CMD_SET_CONFIG_PARAM	Set the total number of ring buffers to use
	XA_CAP_CONFIG_PARAM_RING_NUM	

2.2.1.3 Memory allocation

Table 2-7 List of Memory allocation Commands

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_GET_MEMTABS_SIZE	Get the size of the memory structures to be allocated for the plugin tables
	Null	
2	XA_API_CMD_SET_MEMTABS_PTR	Pass the memory structure pointer allocated for the tables
	Null	
3	XA_API_CMD_INIT	Calculate the required sizes for all the memory blocks based on the setting specific parameters
	XA_CMD_TYPE_INIT_API_POST_CONFIG_PARAMS	
4	XA_API_CMD_GET_N_MEMTABS	Obtain the number of memory blocks required by plugin
	Null	
5	XA_API_CMD_GET_MEM_INFO_SIZE	Get the size of the memory type being referred to by the index
	Index	
6	XA_API_CMD_GET_MEM_INFO_ALIGNMENT	Get the alignment information of the memory type being referred to by the index
	Index	
7	XA_API_CMD_GET_MEM_INFO_TYPE	Get the type of memory being referred to by the index
	Index	
8	XA_API_CMD_SET_MEM_PTR	Set the pointer to the memory allocated for the referred index to the input value
	Index	

2.2.1.4 Initialize plugin

Table 2-8 List of initialize commands

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_SET_INPUT_BYTES	Set the number of bytes available in the input buffer
	Null	
2	XA_API_CMD_INPUT_OVER	Signal to the plugin the end of the bit stream in renderer case
	Null	
3	XA_API_CMD_INIT	Setup for the HW operation, and initialize state and configuration structure
	XA_CMD_TYPE_INIT_PROCESS	
4	XA_API_CMD_INIT	Check if the initialization process has completed
	XA_CMD_TYPE_INIT_DONE_QUERY	
5	XA_API_CMD_GET_CURIDX_INPUT_BUF	Get the number of input buffer bytes consumed
	Null	

2.2.1.5 Getting parameters

Table 2-9 List of Get commands for renderer

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM sample bit width to 16 or 24 bits
	XA_RDR_CONFIG_PARAM_PCM_WIDTH	
2	XA_API_CMD_GET_CONFIG_PARAM	Get the input PCM channels (support monaural, stereo, 4 channels, 6 channels, 8 channels)
	XA_RDR_CONFIG_PARAM_CHANNELS	
3	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM sampling frequency (supported 32000/44100/48000Hz)
	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	
4	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM frame size
	XA_RDR_CONFIG_PARAM_FRAME_SIZE	
5	XA_API_CMD_GET_CONFIG_PARAM	Get Renderer output destination Audio 1 st device
	XA_RDR_CONFIG_PARAM_OUTPUT1	
6	XA_API_CMD_GET_CONFIG_PARAM	Get ADMA channel number usage for Audio 1 st device
	XA_RDR_CONFIG_PARAM_DMACHANNEL1	
7	XA_API_CMD_GET_CONFIG_PARAM	Get Renderer output destination Audio 2 nd device
	XA_RDR_CONFIG_PARAM_OUTPUT2	
8	XA_API_CMD_GET_CONFIG_PARAM	Get ADMA channel number usage for Audio 2 nd device
	XA_RDR_CONFIG_PARAM_DMACHANNEL2	
9	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM sampling frequency
	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	
10	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM volume rate compare with input PCM
	XA_RDR_CONFIG_PARAM_VOLUME_RATE	
11	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM channels (support maximum 2 channels)
	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	
12	XA_API_CMD_GET_CONFIG_PARAM	Get the MIX module usage of Renderer (value 1/0 to used/unused mix function)
	XA_RDR_CONFIG_PARAM_MIX_CONTROL	
13	XA_API_CMD_GET_CONFIG_PARAM	Get the operation state of Renderer plugin (RUN/PAUSE/IDLE/RESET)
	XA_RDR_CONFIG_PARAM_STATE	
14	XA_API_CMD_GET_CONFIG_PARAM	Get the total number of ring buffers
	XA_RDR_CONFIG_PARAM_RING_NUM	

Table 2-10 List of Get commands for capture

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM sample bit width to 16 or 24 bits
	XA_CAP_CONFIG_PARAM_PCM_WIDTH	
2	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM channels (Maximum is 2 channels)
	XA_CAP_CONFIG_PARAM_CHANNELS	
3	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM sampling frequency (supported 32000/44100/48000Hz)
	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	
4	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM frame size
	XA_CAP_CONFIG_PARAM_FRAME_SIZE	
5	XA_API_CMD_GET_CONFIG_PARAM	Get Capture input source Audio 1 st device
	XA_CAP_CONFIG_PARAM_INPUT1	
6	XA_API_CMD_GET_CONFIG_PARAM	Get ADMA channel number usage for Audio device 1st
	XA_CAP_CONFIG_PARAM_DMACHANNEL1	
7	XA_API_CMD_GET_CONFIG_PARAM	Get Capture input destination Audio 2 nd device
	XA_CAP_CONFIG_PARAM_INPUT2	
8	XA_API_CMD_GET_CONFIG_PARAM	Get ADMA channel number usage for Audio 2 nd device
	XA_CAP_CONFIG_PARAM_DMACHANNEL2	
9	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM sampling frequency
	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	
10	XA_API_CMD_GET_CONFIG_PARAM	Get the output PCM volume rate compare with input PCM
	XA_CAP_CONFIG_PARAM_VOLUME_RATE	
11	XA_API_CMD_GET_CONFIG_PARAM	Get the operation state of Capture plugin (RUN/PAUSE/IDLE/RESET)
	XA_CAP_CONFIG_PARAM_STATE	
12	XA_API_CMD_GET_CONFIG_PARAM	Get the total number of ring buffers
	XA_CAP_CONFIG_PARAM_RING_NUM	

2.2.1.6 Execution

Table 2-11 List of execution commands

upper stage : Command / lower step : Subcommand		Description
1	XA_API_CMD_INPUT_OVER	Stop capture in capture case
	Null	
2	XA_API_CMD_SET_INPUT_BYTES	Set the number of bytes available in the input buffer
	Null	
3	XA_API_CMD_EXECUTE	Execute the capture
	XA_CMD_TYPE_DO_EXECUTE	
4	XA_API_CMD_EXECUTE	Check if the execution process has completed
	XA_CMD_TYPE_DONE_QUERY	
5	XA_API_CMD_GET_OUTPUT_BYTES	Get the number of bytes output by the plugin in the last frame
	Null	
6	XA_API_CMD_GET_CURIDX_INPUT_BUF	Get the number of input buffer bytes consumed
	Null	

2.2.2 Detail of Command Specifications

The next sections describe this library command functions by using the description format below.

Subcommand	Name of subcommand
Description	Outlines the function
Arguments	Describes the arguments for the function
Return value	Return values of function
Restrictions	Provides information such as precautions in using the function

[Note] This syntax format complies with ANSI-C.

2.2.2.1 XA_API_CMD_GET_LIB_ID_STRINGS command

Subcommand	XA_CMD_TYPE_LIB_VERSION	
Description	This command obtains the version of the library in the form of a string. The maximum length of the string that the library will provide is 30 bytes. Therefore the application shall pass a pointer to a buffer of a minimum size of 30 bytes. This command is optional.	
Arguments	p_xa_module_obj	
	NULL	
	i_cmd	
	XA_API_CMD_GET_LIB_ID_STRINGS	
	i_idx	
	XA_CMD_TYPE_LIB_VERSION	
	pv_value	
	Pointer to a character buffer in which the version of the library is returned	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	pv_value is NULL.
Restrictions	-	

Example

```
char lib_version[30];
res = (*api_func)(NULL,
                  XA_API_CMD_GET_LIB_ID_STRINGS,
                  XA_CMD_TYPE_LIB_VERSION,
                  (pVOID) lib_version);
```

Subcommand	XA_CMD_TYPE_API_VERSION	
Description	This command obtains the version of the API in the form of a string. The maximum length of the string that the library will provide is 30 bytes. Therefore the application shall pass a pointer to a buffer of a minimum size of 30 bytes. This command is optional.	
Arguments	p_xa_module_obj	
	NULL	
	i_cmd	
	XA_API_CMD_GET_LIB_ID_STRINGS	
	i_idx	
	XA_CMD_TYPE_API_VERSION	
	pv_value	
	Pointer to a character buffer in which the version of the API is returned	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	pv_value is NULL.
Restrictions	-	

Example

```
char api_version[30];
res = (*api_func)(NULL,
                  XA_API_CMD_GET_LIB_ID_STRINGS,
                  XA_CMD_TYPE_API_VERSION,
                  (pVOID) api_version);
```

2.2.2.2 XA_API_CMD_GET_API_SIZE command

Subcommand	(None)	
Description	This command is used to obtain the size of the API structure, in order to allocate memory for the API structure.	
Arguments	p_xa_module_obj	
	NULL	
	i_cmd	
	XA_API_CMD_GET_API_SIZE	
	i_idx	
	Null	
	pv_value	
	Pointer to API size variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	pv_value is NULL.
Restrictions	The application shall allocate memory with an alignment of 4 bytes.	

Example

```
WORD32 api_size;
res = (*api_func)(api_obj,
                  XA_CMD_TYPE_API_SIZE,
                  0,
                  &api_size);
```

2.2.2.3 XA_API_CMD_INIT command

Subcommand	XA_CMD_TYPE_INIT_API_PRE_CONFIG_PARAMS	
Description	This command is used to set the default value of the configuration parameters.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_INIT	
	i_idx	
	XA_CMD_TYPE_INIT_API_PRE_CONFIG_PARAMS	
	pv_value	
	NULL	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
Restrictions	-	

Example

```
res = (*api_func)(api_obj,
                  XA_API_CMD_INIT,
                  XA_CMD_TYPE_INIT_API_PRE_CONFIG_PARAMS,
                  NULL);
```

Subcommand	XA_CMD_TYPE_INIT_API_POST_CONFIG_PARAMS	
Description	This command is used to calculate the sizes of all the memory blocks required by the application. It should occur after the plugin specific parameters have been set.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_INIT	
	i_idx	
	XA_CMD_TYPE_INIT_API_POST_CONFIG_PARAMS	
	pv_value	
	NULL	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before set memory table step)
	XA_CAP_EXEC_FATAL_INTERNAL (in Capture case) XA_RDR_EXEC_FATAL_INTERNAL (in Renderer case)	Invalid connection device setting path (i.e. setting SRC or SSI module for both device1 and device2)
Restrictions	-	

Example

```
res = (*api_func)(api_obj,
                  XA_API_CMD_INIT,
                  XA_CMD_TYPE_INIT_API_POST_CONFIG_PARAMS,
                  NULL);
```

Subcommand	XA_CMD_TYPE_INIT_PROCESS	
Description	<p>Setup for the HW operation, and initialize state and configuration structure. No output data is created during initialization. In this state, plugin will check all hardware modules. If a module is busy, plugin will try to establish connection with next available one. If all modules are busy, this command will return error code and stop immediately.</p> <p>In case of using mix function with a different plugin (*), if user set different data format (PCM width, output sampling rate, output channel), this command will return error and stop immediately.</p>	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_INIT	
	i_idx	
	XA_CMD_TYPE_INIT_PROCESS	
	pv_value	
	NULL	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_EXEC_FATAL_STATE (in Capture case) XA_RDR_EXEC_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. called before post-configuration step, or run post-configuration without persistent buffer allocation, or without valid shared buffers, built-in descriptor memory allocation (in case of ADMAC used))
	XA_CAP_EXEC_FATAL_HW (in Capture case) XA_RDR_EXEC_FATAL_HW (in Renderer case)	All hardware resource are not available.
	XA_RDR_EXEC_FATAL_FORMAT_MISMATCH (only Renderer)	The configured output format is different between this plugin and the plugin it is intended to mix with.
Restrictions	-	

Example

```
res = (*api_func)(api_obj,
                  XA_API_CMD_INIT,
                  XA_CMD_TYPE_INIT_PROCESS,
                  NULL);
```


Subcommand	XA_CMD_TYPE_INIT_DONE_QUERY	
Description	This command checks to see if the initialization process has completed. If it has, the flag value is set to 1; else, it is set to zero. A pointer to the flag variable is passed as an argument.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_INIT	
	i_idx	
	XA_CMD_TYPE_INIT_DONE_QUERY	
	pv_value	
	Pointer to flag that indicates the completion of initialization process	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_EXEC_FATAL_STATE (in Capture case) (XA_RDR_EXEC_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before post-configuration step)
Restrictions	-	

Example

```
WORD32 done;
res = (*api_func)(api_obj,
                  XA_API_CMD_INIT,
                  XA_CMD_TYPE_INIT_DONE_QUERY,
                  &done);
```

2.2.2.4 XA_API_CMD_GET_MEMTABS_SIZE command

Subcommand	None	
Description	This command is used to obtain the size of the table used to hold the memory blocks required for the plugin operation. The API returns the total size of the required table. A pointer to the size variable is sent with this API command and the plugin writes the value to the variable.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_MEMTABS_SIZE	
	i_idx	
	Null	
	pv_value	
Pointer to memory size variable		
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before pre-configuration step)
	Restrictions	-

Example

```
WORD32 memtab_size;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_MEMTABS_SIZE,
                  0,
                  &memtab_size);
```

2.2.2.5 XA_API_CMD_SET_MEMTABS_PTR command

Subcommand	None	
Description	This command is used to set the memory structure pointer in the library to the allocated value.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_MEMTABS_PTR	
	i_idx	
	Null	
	pv_value	
	Allocated pointer	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj or pv_value is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
pVOID memtab_ptr;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_MEMTABS_PTR,
                  0,
                  memtab_ptr);
```

2.2.2.6 XA_API_CMD_GET_N_MEMTABS command

Subcommand	None	
Description	This command is used to obtain the number of memory blocks needed by the plugin. This value is used as the iteration counter for the allocation of the memory blocks. A pointer to each memory block will be placed in the previously allocated memory tables. The pointer to the variable is passed to the API and the plugin writes the value to this variable.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_N_MEMTABS	
	i_idx	
	Null	
	pv_value	
	Pointer to variable of number of memory blocks required to be allocated	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
Restrictions	-	

Example

```
WORD32 n_memtab;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_N_MEMTABS,
                  0,
                  &n_memtab);
```

2.2.2.7 XA_API_CMD_GET_MEM_INFO_SIZE command

Subcommand	Memory index	
Description	This command obtains the size of the memory type being referred to by the index. The size in bytes is returned in the variable pointed to by the final argument.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_MEM_INFO_SIZE	
	i_idx	
	Index of the memory 0 - Persistent Area 1 - Input Buffer (in Renderer case) 1 - Output Buffer (in Capture case) 2 - Built-in memory	
	pv_value	
	Pointer to memory size	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned 4 bytes
	XA_API_FATAL_INVALID_CMD_TYPE	FIFO is used when setting for built-in memory
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before post-configuration step)
Restrictions	The index of built-in memory is only valid when 1 st DMA device is ADMAC.	

```
WORD32 mem_size;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_MEM_INFO_SIZE,
                  index,
                  &mem_size);
```

2.2.2.8 XA_API_CMD_GET_MEM_INFO_ALIGNMENT command

Subcommand	Memory index	
Description	This command gets the alignment information of the memory-type being referred to by the index. The alignment required in bytes is returned to the application.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_MEM_INFO_ALIGNMENT	
	i_idx	
	Index of the memory 0 - Persistent Area 1 - Input Buffer (in Renderer case) 1 - Output Buffer (in Capture case) 2 - Built-in memory	
	pv_value	
Return value	Pointer to the alignment info variable	
	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned 4 bytes
	XA_API_FATAL_INVALID_CMD_TYPE	FIFO is used when setting for built-in memory
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before post-configuration step)
Restrictions	The index of built-in memory is only valid when 1 st DMA device is ADMAC.	

Example

```
WORD32 mem_align;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_MEM_INFO_ALIGNMENT,
                  index,
                  &mem_align);
```

2.2.2.9 XA_API_CMD_GET_MEM_INFO_TYPE command

Subcommand	Memory index	
Description	This command gets the alignment information of the memory-type being referred to by the index. The alignment required in bytes is returned to the application.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_MEM_INFO_TYPE	
	i_idx	
	Index of the memory 0 - Persistent Area 1 - Input Buffer (in renderer case) 1 - Output Buffer (in capture case) 2 - Built-in memory	
	pv_value	
Return value	Pointer to the memory type variable	
	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned 4 bytes
	XA_API_FATAL_INVALID_CMD_TYPE	FIFO is used when setting for built-in memory
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before post-configuration step)
Restrictions	The index of built-in memory is only valid when 1 st DMA device is ADMAC.	

Example

```
WORD32 mem_type;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_MEM_INFO_TYPE,
                  index,
                  &mem_type);
```

2.2.2.10 XA_API_CMD_SET_MEM_PTR command

Subcommand	Memory index	
Description	This command passes to the plugin the pointer to the allocated memory. This is then stored in the memory tables structure allocated earlier. For the input and output buffers, it maps all data buffers to shared memory/local memory and data will be transferred in an order from the first to the last index of shared buffers. It is legitimate to execute this command during the main plugin loop.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_MEM_PTR	
	i_idx	
	Index of the memory 0 - Persistent Area 1 - Input Buffer (renderer case) 1 - Output Buffer (capture case) 2 - Built-in memory	
	pv_value	
	Pointer to the memory block	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes. pv_value is not aligned to required alignment for the requested memory block.
	XA_API_FATAL_INVALID_CMD_TYPE	FIFO is used when setting for built-in memory
	XA_CAP_CONFIG_FATAL_STATE (in Capture case) XA_RDR_CONFIG_FATAL_STATE (in Renderer case)	Incorrect sequence call (i.e. call before post-configuration step)
Restrictions	The pointer must be correctly aligned to the requirements. The index of built-in memory is only valid when 1 st DMA device is ADMAC.	

Example

```
pVOID addr;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_MEM_PTR,
                  index,
                  addr);
```


2.2.2.11 XA_API_CMD_INPUT_OVER command

Subcommand	None	
Description	This command is used to tell the plugin that the input signal is over. The execution or initialization step will continue in loop until it all the remaining input data is processed.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_INPUT_OVER	
	i_idx	
	Null	
	pv_value	
	NULL	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_EXEC_FATAL_STATE (only for Capture)	Incorrect sequence call (i.e. call before initialization step – init process)
Restrictions	-	

Example

```
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_INPUT_OVER,
                  0,
                  NULL);
```

2.2.2.12 XA_API_CMD_SET_INPUT_BYTES command

Subcommand	None	
Description	<p>In capture this command will do nothing. The purpose of this command is filled the full list of standard API.</p> <p>In renderer this command will set number of bytes available in the input buffer. If renderer's operation state is reset, it will re-setup and start HW modules and change the operation state to run.</p>	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_INPUT_BYTES	
	i_idx	
	Null	
	pv_value	
	Pointer to the input byte variable (Any value is OK with Capture case)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes in renderer case.
	XA_RDR_EXEC_FATAL_INPUT (only for Renderer)	Invalid input buffer size (i.e. minus buffer size or buffer size is not align with sample size)
	XA_RDR_EXEC_FATAL_STATE (only for Renderer)	Input memory is not allocated before or incorrect sequence call
Restrictions	-	

Example

```
WORD32 filled;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_INPUT_BYTES,
                  0,
                  &filled);
```

2.2.2.13 XA_API_CMD_GET_CURIDX_INPUT_BUF command

Subcommand	None	
Description	In Capture, this command will return value 0 each time it's called. In Renderer, this command will return number of input buffer bytes consumed.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CURIDX_INPUT_BUF	
	i_idx	
	Null	
	pv_value	
	Pointer to number variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_EXEC_FATAL_STATE (only for Renderer)	Input memory is not allocated before.
Restrictions	-	

Example

```
WORD32 consumed;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CURIDX_INPUT_BUF,
                  0,
                  &consumed);
```

2.2.2.14 XA_API_CMD_EXECUTE command

Subcommand	XA_CMD_TYPE_DO_EXECUTE	
Description	This command executes Capture. If capture's operation state is reset, it will re-setup and start HW modules and change the operation state to run.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_EXECUTE	
	i_idx	
	XA_CMD_TYPE_DO_EXECUTE	
	pv_value	
	NULL	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_EXEC_FATAL_STATE (only implement in Capture case)	Incorrect sequence call (i.e. call before initialization step) or output memory is not allocated before.
Restrictions	-	

Example

```
res = (*api_func)(api_obj,
                  XA_API_CMD_EXECUTE,
                  XA_CMD_TYPE_DO_EXECUTE,
                  NULL);
```

Subcommand	XA_CMD_TYPE_DONE_QUERY	
Description	This command checks to see if the end of processing has been reached. If it is, the flag value is set to 1; else, it is set to zero. The pointer to the flag is passed as an argument. Processing by the plugin can continue for several invocations of the DO_EXECUTE command after the last input data has been passed to the plugin, so the application should not assume that the plugin has finished generating all its output until so indicated by this command.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_EXECUTE	
	i_idx	
	XA_CMD_TYPE_DONE_QUERY	
	pv_value	
	Pointer to the flag variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_RDR_EXEC_FATAL_STATE (only implement in Renderer)	Incorrect sequence call (i.e. call before initialization step)
Restrictions	-	

Example

```
WORD32 done;
res = (*api_func)(api_obj,
                  XA_API_CMD_EXECUTE,
                  XA_CMD_TYPE_DONE_QUERY,
                  &done);
```

2.2.2.15 XA_API_CMD_GET_OUTPUT_BYTES command

Subcommand	None	
Description	This command obtains the number of bytes output by the plugin during the last execution.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_OUTPUT_BYTES	
	i_idx	
	Null	
	pv_value	
	Pointer to the flag variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj or pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_EXEC_FATAL_STATE (only Capture)	Incorrect sequence call (i.e. call before initialization step) or output memory is not allocated before.
Restrictions	-	

Example

```
WORD32 produced;  
res = (*api_func)(api_obj,  
                  XA_API_CMD_GET_OUTPUT_BYTES,  
                  0,  
                  &produced);
```

2.2.2.16 XA_API_CMD_SET_CONFIG_PARAM command

2.2.2.16.1 Set command for Renderer

Subcommand	XA_RDR_CONFIG_PARAM_PCM_WIDTH	
Description	Set the PCM sample bit width to 16 or 24 bits	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_PCM_WIDTH	
	pv_value	
	Pointer to the sample bit width variable Valid value: 16 or 24 Default value: 16	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_PCM_WIDTH	PCM sample width size is not valid.
	XA_RDR_CONFIG_FATAL_ERR_MONO_24BIT	Setting is invalid.
Restrictions	-	

Example

```
WORD32 pcm_width;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_PCM_WIDTH,
                  &pcm_width);
```

Subcommand	XA_RDR_CONFIG_PARAM_CHANNELS	
Description	Set the input PCM channels number	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_CHANNELS	
	pv_value	
Return value	Pointer to the input PCM channels variable Valid value: 1 (monaural), 2 (stereo), 4 (4 channels), 6 (6 channels), 8 (8 channels) Default value: 2 (stereo)	
	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_CHANNELS	Input PCM channels are invalid.
Restrictions	XA_RDR_CONFIG_FATAL_ERR_MONO_24BIT	Setting is invalid.
	-	

Example

```
WORD32 ch;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_CHANNELS,
                  &ch);
```


Subcommand	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	
Description	Set the PCM sampling frequency	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	
	pv_value	
	Pointer to the input sampling frequency variable Valid value: 32,000 / 44,100 / 48,000 Hz Default value: 44,100 Hz	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_SAMPLE_RATE	Input PCM sampling frequency is invalid.
Restrictions	-	

Example

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_RDR_CONFIG_PARAM_FRAME_SIZE	
Description	Set the PCM frame size	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_FRAME_SIZE	
	pv_value	
	Pointer to the input frame size variable Valid value: frame size is power of two value Default value: 1024	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_FRAME_SIZE	PCM frame size value is not the power of two.
Restrictions	-	

Example

```
WORD32 frame_size;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_FRAME_SIZE,
                  &frame_size);
```

Subcommand	XA_RDR_CONFIG_PARAM_OUTPUT1	
Description	Set 1 st output destination device for Renderer	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUTPUT1	
	pv_value	
	Pointer to the output device index Default value: 0 (use SSI0)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_SOURCE	The output source is invalid.
Restrictions	-	

[Note] Value range of output source relates to the PDMA and ADMAC source destination enum. It is presented below:

SSI module index: SSI_MODULE_MIN (0) <= output_source <= SSI_MODULE_MAX (97)

SCU SRC module index: SCU_SRC_INPUT_MODULE_MIN (110) <= output_source <= SCU_SRC_INPUT_MODULE_MAX (119)

Other index: reserved, not used.

The output source information is necessary. Default value is 140 means that it is fault if output source is not set by user.

Example

```
WORD32 output_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUTPUT1,
                  &output_source);
```

Subcommand	XA_RDR_CONFIG_PARAM_DMACHANNEL1	
Description	Set ADMA channel number usage for 1 st Audio device.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_DMACHANNEL1	
	pv_value	
	Pointer to the Audio-DMAC / Audio-DMAC-peripheral-peripheral channels number	
	Valid value: ADMAC_CH[29-60] : Use Audio-DMAC to transfer ADMACPP_CH[00-28] : Use Audio-DMAC-pp extended to transfer	
	Default value: 0 - ADMACPP_CH00	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_DMACHANNEL	DMA channel is invalid.
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_DMACHANNEL1,
                  &dma_channel);
```

Subcommand	XA_RDR_CONFIG_PARAM_OUTPUT2	
Description	Set 2 nd output destination device for Renderer	
Arguments	p_xa_module_obj	
	Pointer to API Structure.	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUTPUT2	
	pv_value	
	Pointer to the output device Default value: 140 (the 2 nd output device is not used)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_SOURCE	Output source is invalid
Restrictions	-	

[Note] Value range of output source relates to the PDMA and ADMAC source destination enum. It is presented below:

SSI module index: SSI_MODULE_MIN (0) <= output_source <= SSI_MODULE_MAX (97)

SCU SRC module index: SCU_SRC_INPUT_MODULE_MIN (110) <= output_source <= SCU_SRC_INPUT_MODULE_MAX (119)

Other index: reserved, not used.

The output source information is necessary. Default value is 140 means that it is fault if output source is not set by user.

Example

```
WORD32 output_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUTPUT2,
                  &output_source);
```

Subcommand	XA_RDR_CONFIG_PARAM_DMACHANNEL2	
Description	Set ADMA channel number usage for 2 nd Audio device.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_DMACHANNEL2	
	pv_value	
	Pointer to the Audio-DMAC / Audio-DMAC-peripheral-peripheral channels number	
	Valid value: ADMAC_CH[29-60] : Use Audio-DMAC to transfer ADMACPP_CH[00-28] : Use Audio-DMAC-pp extended to transfer	
	Default value: 1 - ADMACPP_CH01	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_DMACHANNEL	DMA channel is invalid.
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_DMACHANNEL2,
                  &dma_channel);
```

Subcommand	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	
Description	Set output sample rate in Sampling Rate Converter (SRC) of Sampling Rate Converter Unit (SCU). If this setting value is different from input sample rate of PCM, SRC connection will be enabled even without setting connection device path. And the connection will automatically use the available Audio-DMAC channel.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	
	pv_value	
	Pointer to the output sampling frequency variable Valid value: 32,000 / 44,100 / 48,000 (Hz) Default value: 44,100 Hz	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_SAMPLE_RATE	Output sample rate is invalid.
Restrictions	-	

Example:

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_RDR_CONFIG_PARAM_VOLUME_RATE	
Description	Set the output PCM volume rate in Digital Volume and Mute Function (DVC), and Mixer (MIX) (if mix function is used) of Sampling Rate Converter Unit (SCU). Any set value except for 0xFFFF FFFF (disable DVC) enables DVC of SCU module and the connection will be established even without setting connection path. This command can be set during plugin execution to update the output volume rate.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_VOLUME_RATE	
	pv_value	
	Pointer to the volume ratio number (using Fix-point Q3.20) Valid value: 0xFFFF FFFF : disable DVC module [0, 0x7F FFFF] : setting volume rate value Default value: 0xFFFF FFFF	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
	XA_RDR_CONFIG_NONFATAL_VOLUME_RATE	Volume rate value is invalid.
Restrictions	To use volume update function, DVC must be enabled in advance (before Renderer goes to post-configuration state).	

Example:

```
WORD32 vol_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_VOLUME_RATE,
                  &vol_rate);
```


Subcommand	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	
Description	Set the output PCM channels number. If this setting is difference between input and output channel, the CTU module will be enabled to perform channel transfer.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	
	pv_value	
	Pointer to the output PCM channels variable Valid value: 1 (monaural), 2 (stereo) Default value: 2 (stereo)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_ERR_CHANNELS	Output PCM channels is invalid.
	XA_RDR_CONFIG_FATAL_ERR_MONO_24BIT	Setting is invalid.
Restrictions	-	

Example

```
WORD32 ch_out;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUT_CHANNELS,
                  &ch_out);
```

Subcommand	XA_RDR_CONFIG_PARAM_MIX_CONTROL	
Description	Set the MIX module usage for Renderer	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_MIX_CONTROL	
	pv_value	
	Pointer to the MIX control flag variable Valid value: 0 (not use mix function), 1 (use mix function) Default value: 0	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_RDR_CONFIG_NONFATAL_MIX_CONTROL	The setting value is invalid.
Restrictions	-	

Example

```
WORD32 mix_ctl;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_MIX_CONTROL,
                  &mix_ctl);
```

Subcommand	XA_RDR_CONFIG_PARAM_STATE	
Description	Set the operation state for Renderer plugin. Renderer can change from RUN to PAUSE, from RUN to IDLE, from PAUSE to IDLE, from PAUSE to RUN, from RUN to RESET and from PAUSE to RESET, RESET to IDLE during plugin execution. This command only has effect when Renderer is in the execution state. Otherwise, it will do nothing and return no error.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_STATE	
	pv_value	
	Pointer to the expected state of plugin Valid value: 0 - XA_RDR_STATE_RUN: execute data to output 1 - XA_RDR_STATE_IDLE: stop and destroy plugin 2 - XA_RDR_STATE_PAUSE: pause the executing data to output 3 - XA_RDR_STATE_RESET: reset the plugin Default value: 0	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
	XA_RDR_EXEC_FATAL_HW	Cannot reset the plugin
	XA_RDR_CONFIG_NONFATAL_OPERATION	The setting value is invalid.
Restrictions	-	

Example

```
WORD32 state;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_STATE,
                  &state);
```

Subcommand	XA_RDR_CONFIG_PARAM_RING_NUM	
Description	Set the total number of ring buffers to use	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_RING_NUM	
	pv_value	
	Pointer to the total number of ring buffers Valid value: 2, 4 Default value: 2	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step or after post-configuration step)
	XA_RDR_CONFIG_FATAL_RING_NUM	Ring num value is invalid
Restrictions	-	

Example

```
WORD32 ring_num;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_RING_NUM,
                  &ring_num);
```

2.2.2.16.2 Set command for capture

Subcommand	XA_CAP_CONFIG_PARAM_PCM_WIDTH	
Description	Set the PCM sample bit width to 16 or 24 bits	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_PCM_WIDTH	
	pv_value	
	Pointer to the sample bit width variable	
Return value	Valid value: 16 or 24 Default value: 16	
	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_PCM_WIDTH	PCM sample width size is not valid.
Restrictions	XA_CAP_CONFIG_FATAL_ERR_MONO_24BIT	Setting is invalid.
	-	

Example

```
WORD32 pcm_width;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_PCM_WIDTH,
                  &pcm_width);
```

Subcommand	XA_CAP_CONFIG_PARAM_CHANNELS	
Description	Set the PCM channels number	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_CHANNELS	
	pv_value	
	Pointer to the input channels variable	
Return value	Valid value: 1 (monaural), 2 (stereo) Default value: 2 (stereo)	
	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_CHANNELS	PCM input channels is invalid.
Restrictions	XA_CAP_CONFIG_FATAL_ERR_MONO_24BIT	Setting is invalid.
	-	

Example

```
WORD32 ch;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_CHANNELS,
                  &ch);
```

Subcommand	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	
Description	Set the PCM sampling frequency	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	
	pv_value	
	Pointer to the input sampling frequency variable	
Return value	Valid value: 32,000 / 44,100 / 48,000 (Hz) Default value: 44,100	
	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
Restrictions	XA_CAP_CONFIG_NONFATAL_ERR_SAMPLE_RATE	PCM input sampling frequency is invalid.
	-	

Example

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_CAP_CONFIG_PARAM_FRAME_SIZE	
Description	Set the PCM frame size	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_FRAME_SIZE	
	pv_value	
	Pointer to the input frame size variable Valid value: frame size is power of two value Default value: 1024	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_FRAME_SIZE	PCM frame size value is not the power of two.
Restrictions	-	

Example

```
WORD32 frame_size;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_FRAME_SIZE,
                  &frame_size);
```


Subcommand	XA_CAP_CONFIG_PARAM_INPUT1	
Description	Set 1 st input device for Capture	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_INPUT1	
	pv_value	
	Pointer to the input source value Default value: 10 (SSI1)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_SOURCE	PCM input source is invalid.
Restrictions	-	

[Note] Value range of input source relates to the PDMA and ADMAC source destination enum. It is presented below:

SSI module index: SSI_MODULE_MIN (0) <= output_source <= SSI_MODULE_MAX (97)

SCU SRC module index: SCU_SRC_INPUT_MODULE_MIN (110) <= output_source <= SCU_SRC_INPUT_MODULE_MAX (119)

Other index: reserved, not used.

The output source information is necessary. Default value is 140 means that it is fault if output source is not set by user.

Example

```
WORD32 input_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_INPUT1,
                  &input_source);
```

Subcommand	XA_CAP_CONFIG_PARAM_DMACHANNEL1	
Description	Set ADMA channel number usage for 1 st Audio device	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_DMACHANNEL1	
	pv_value	
	Pointer to the ADMA channels number Valid value: ADMAC_CH[29-60] : Use Audio-DMAC to transfer ADMACPP_CH[0-28] : Use Audio-DMAC-pp extended to transfer Default value: ADMACPP_CH10	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_DMACHANNEL	PCM DMA channel is invalid.
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_DMACHANNEL1,
                  &dma_channel);
```

Subcommand	XA_CAP_CONFIG_PARAM_INPUT2	
Description	Set 2 nd input device for Capture	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_INPUT2	
	pv_value	
	Pointer to the input source value Default value: 140 (the 2 nd input device is not used)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_SOURCE	PCM input source is invalid.
Restrictions	-	

[Note] Value range of input source relates to the PDMA and ADMAC source destination enum. It is presented below:

SSI module index: SSI_MODULE_MIN (0) <= output_source <= SSI_MODULE_MAX (97)

SCU SRC module index: SCU_SRC_INPUT_MODULE_MIN (110) <= output_source <= SCU_SRC_INPUT_MODULE_MAX (119)

Other index: reserved, not used.

The output source information is necessary. Default value is 140 means that it is fault if output source is not set by user.

Example

```
WORD32 input_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_INPUT2,
                  &input_source);
```

Subcommand	XA_CAP_CONFIG_PARAM_DMACHANNEL2	
Description	Set ADMA channel number usage for 2 nd Audio device	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_DMACHANNEL2	
	pv_value	
	Pointer to the ADMA channels number Valid value: ADMAC_CH[0-31] : Audio-DMAC usage channel 0 -31 ADMACPP_CH[0-28] : Audio-DMAC-pp extended usage channel 0-28 Default value: ADMACPP_CH11	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_DMACHANNEL	PCM DMA channel is invalid.
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_DMACHANNEL2,
                  &dma_channel);
```

Subcommand	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	
Description	Set output sample rate in Sampling Rate Converter (SRC) of Sampling Rate Converter Unit (SCU). If this setting value is different from input sample rate of PCM, SRC connection will be enabled even without setting connection device path. And the connection will automatically use the available Audio-DMAC channel.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	
	pv_value	
	Pointer to the output sampling frequency variable Valid value: 32,000 / 44,100 / 48,000 (Hz) Default value: 44,100	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step and after post-configuration step)
	XA_CAP_CONFIG_NONFATAL_ERR_SAMPLE_RATE	PCM output sample rate is invalid.
Restrictions	-	

Example:

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_CAP_CONFIG_PARAM_VOLUME_RATE	
Description	Set the output PCM volume rate in Digital Volume and Mute Function (DVC) of Sampling Rate Converter Unit (SCU). Any set value other than 0xFFFF FFFF (disable DVC) enables DVC of SCU module and the connection will be established even without setting connection path. This command can be set during plugin execution to update the output volume rate.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_VOLUME_RATE	
	pv_value	
	Pointer to the volume ratio number (using Fix-point Q3.20) Valid value: 0xFFFF FFFF : disable DVC module [0, 0x7F FFFF] : setting volume rate value Default value: 0xFFFF FFFF	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
	XA_CAP_CONFIG_NONFATAL_VOLUME_RATE	PCM volume rate value is invalid.
Restrictions	To use volume update function, DVC must be enabled in advance (before Capture goes to post-configuration state).	

Example:

```
WORD32 vol_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_VOLUME_RATE,
                  &vol_rate);
```

Subcommand	XA_CAP_CONFIG_PARAM_STATE	
Description	Set the operation state for Capture plugin. Capture can change from RUN to PAUSE, from RUN to IDLE, from PAUSE to IDLE, from PAUSE to RUN, from RUN to RESET, from PAUSE to RESET, from RESET to IDLE during plugin execution. This command only has effect when Capture is in the execution state. Otherwise, it will do nothing and return no error.	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_STATE	
	pv_value	
	Pointer to the expected state of plugin Valid value: 0 - XA_CAP_STATE_RUN: execute data to output 1 - XA_CAP_STATE_IDLE: stop and destroy plugin 2 - XA_CAP_STATE_PAUSE: pause the executing data to output 3 - XA_CAP_STATE_RESET: reset the plugin Default value: 0	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
	XA_CAP_EXEC_FATAL_HW	Cannot reset the plugin
	XA_CAP_CONFIG_NONFATAL_OPERATION	The setting value is invalid.
Restrictions	-	

Example

```
WORD32 state;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_STATE,
                  &state);
```

Subcommand	XA_CAP_CONFIG_PARAM_RING_NUM	
Description	Set total number of ring buffers to use	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_SET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_RING_NUM	
	pv_value	
	Pointer to the total number of ring buffers Valid value: 2, 4 Default value: 2	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step or after post-configuration step)
	XA_CAP_CONFIG_FATAL_RING_NUM	Ring num value is invalid
Restrictions	-	

Example

```
WORD32 ring_num;
res = (*api_func)(api_obj,
                  XA_API_CMD_SET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_RING_NUM,
                  &ring_num);
```


2.2.2.17 XA_API_CMD_GET_CONFIG_PARAM command

2.2.2.17.1 Get command for renderer

Subcommand	XA_RDR_CONFIG_PARAM_PCM_WIDTH	
Description	Get the PCM sample bit width settings	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_PCM_WIDTH	
	pv_value	
	Pointer to the sample bit width variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 pcm_width;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_PCM_WIDTH,
                  &pcm_width);
```

Subcommand	XA_RDR_CONFIG_PARAM_CHANNELS	
Description	Get the input PCM channels number setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_CHANNELS	
	pv_value	
	Pointer to channels variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 ch;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_CHANNELS,
                  &ch);
```

Subcommand	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	
Description	Get the PCM sampling frequency setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_SAMPLE_RATE	
	pv_value	
	Pointer to sampling frequency variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_RDR_CONFIG_PARAM_FRAME_SIZE	
Description	Get the PCM frame size setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_FRAME_SIZE	
	pv_value	
	Pointer to frame size variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 frame_size;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_FRAME_SIZE,
                  &frame_size);
```

Subcommand	XA_RDR_CONFIG_PARAM_OUTPUT1	
Description	Get 1 st output destination device for Renderer info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUTPUT1	
	pv_value	
	Pointer to the 1st output destination device value	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 output_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUTPUT1,
                  &output_source);
```

Subcommand	XA_RDR_CONFIG_PARAM_DMACHANNEL1	
Description	Get ADMA channel number usage for 1 st Audio device info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_DMACHANNEL1	
	pv_value	
	Pointer to the 1st Audio-DMAC / Audio-DMAC-peripheral-peripheral channel variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_DMACHANNEL1,
                  &dma_channel);
```

Subcommand	XA_RDR_CONFIG_PARAM_OUTPUT2	
Description	Get 2 nd output destination device for Renderer info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUTPUT2	
	pv_value	
	Pointer to the 2nd output destination device value	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 output_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUTPUT2,
                  &output_source);
```

Subcommand	XA_RDR_CONFIG_PARAM_DMACHANNEL2	
Description	Get ADMA channel number usage for 2 nd Audio device info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_DMACHANNEL2	
	pv_value	
	Pointer to the 2nd Audio-DMAC / Audio-DMAC-peripheral-peripheral channel variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_DMACHANNEL2,
                  &dma_channel);
```


Subcommand	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	
Description	Get output sample rate setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE	
	pv_value	
	Pointer to the output sampling frequency variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example:

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUT_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_RDR_CONFIG_PARAM_VOLUME_RATE	
Description	Get the output PCM volume rate setting value	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_VOLUME_RATE	
	pv_value	
	Pointer to the volume ratio number (using Fix-point Q3.20)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example:

```
WORD32 vol_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_VOLUME_RATE,
                  &vol_rate);
```

Subcommand	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	
Description	Get the output PCM channels number setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_OUT_CHANNELS	
	pv_value	
	Pointer to output channels variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 ch_out;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_OUT_CHANNELS,
                  &ch_out);
```

Subcommand	XA_RDR_CONFIG_PARAM_MIX_CONTROL	
Description	Get the MIX module usage of Renderer	
Arguments	p_xa_module_obj	Pointer to API Structure
	i_cmd	XA_API_CMD_GET_CONFIG_PARAM
	i_idx	XA_RDR_CONFIG_PARAM_MIX_CONTROL
	pv_value	Pointer to Mix control flag variable
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 mix_ctl;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_MIX_CONTROL,
                  &mix_ctl);
```

Subcommand	XA_RDR_CONFIG_PARAM_STATE	
Description	Get the current operation state of Renderer plugin	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_STATE	
	pv_value	
	Pointer to the current operation state of plugin	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 cur_state;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_STATE,
                  &cur_state);
```

Subcommand	XA_RDR_CONFIG_PARAM_RING_NUM	
Description	Get the total number of ring buffers	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_RDR_CONFIG_PARAM_RING_NUM	
	pv_value	
	Pointer to the total number of ring buffers	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_RDR_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 ring_num;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_RDR_CONFIG_PARAM_RING_NUM,
                  &ring_num);
```

2.2.2.17.2 Get command for capture

Subcommand	XA_CAP_CONFIG_PARAM_PCM_WIDTH	
Description	Get the PCM sample bit width settings	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_PCM_WIDTH	
	pv_value	
	Pointer to the sample bit width variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. called before pre-configuration step)
Restrictions	-	

Example

```
WORD32 pcm_width;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_PCM_WIDTH,
                  &pcm_width);
```

Subcommand	XA_CAP_CONFIG_PARAM_CHANNELS	
Description	Get the PCM channels number setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_CHANNELS	
	pv_value	
	Pointer to channels variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 ch;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_CHANNELS,
                  &ch);
```


Subcommand	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	
Description	Get the PCM sampling frequency setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_SAMPLE_RATE	
	pv_value	
	Pointer to sampling frequency variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_CAP_CONFIG_PARAM_FRAME_SIZE	
Description	Get the PCM frame size setting	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_FRAME_SIZE	
	pv_value	
	Pointer to frame size variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 frame_size;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_FRAME_SIZE,
                  &frame_size);
```

Subcommand	XA_CAP_CONFIG_PARAM_INPUT1	
Description	Get 1 st input source device for Capture info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_INPUT1	
	pv_value	
	Pointer to the 1st input device value	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 input_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_INPUT1,
                  &input_source);
```

Subcommand	XA_CAP_CONFIG_PARAM_DMACHANNEL1	
Description	Get ADMA channel number usage for 1 st Audio device info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_DMACHANNEL1	
	pv_value	
	Pointer to the 1st Audio-DMAC channel	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_DMACHANNEL1,
                  &dma_channel);
```

Subcommand	XA_CAP_CONFIG_PARAM_INPUT2	
Description	Get 2 nd input source device for Capture info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_INPUT2	
	pv_value	
	Pointer to the 2nd input source device value	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 input_source;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_INPUT2,
                  &input_source);
```

Subcommand	XA_CAP_CONFIG_PARAM_DMACHANNEL2	
Description	Get ADMA channel number usage for 2 nd Audio device info	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_DMACHANNEL2	
	pv_value	
	Pointer to the 2nd Audio-DMAC channel	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 dma_channel;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_DMACHANNEL2,
                  &dma_channel);
```

Subcommand	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	
Description	Get output sample rate setting value	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE	
	pv_value	
	Pointer to the output sampling frequency variable	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example:

```
WORD32 sample_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_OUT_SAMPLE_RATE,
                  &sample_rate);
```

Subcommand	XA_CAP_CONFIG_PARAM_VOLUME_RATE	
Description	Get the output PCM volume rate setting value	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_VOLUME_RATE	
	pv_value	
	Pointer to the volume ratio number (using Fix-point Q3.20)	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 vol_rate;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_VOLUME_RATE,
                  &vol_rate);
```


Subcommand	XA_CAP_CONFIG_PARAM_STATE	
Description	Get the current operation state of Capture plugin	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_STATE	
	pv_value	
	Pointer to the current operation state of plugin	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 cur_state;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_STATE,
                  &cur_state);
```

Subcommand	XA_CAP_CONFIG_PARAM_RING_NUM	
Description	Get the total number of ring buffers	
Arguments	p_xa_module_obj	
	Pointer to API Structure	
	i_cmd	
	XA_API_CMD_GET_CONFIG_PARAM	
	i_idx	
	XA_CAP_CONFIG_PARAM_RING_NUM	
	pv_value	
	Pointer to the total number of ring buffers	
Return value	XA_NO_ERROR	Normally ends.
	XA_API_FATAL_MEM_ALLOC	p_xa_module_obj / pv_value is NULL.
	XA_API_FATAL_MEM_ALIGN	p_xa_module_obj is not aligned to 4 bytes.
	XA_CAP_CONFIG_FATAL_STATE	Incorrect sequence call (i.e. call before pre-configuration step)
Restrictions	-	

Example

```
WORD32 ring_num;
res = (*api_func)(api_obj,
                  XA_API_CMD_GET_CONFIG_PARAM,
                  XA_CAP_CONFIG_PARAM_RING_NUM,
                  &ring_num);
```

2.3 Structures

Table 2-12 lists the structures for this software. The user should reserve areas required for these structures. For detailed specifications of these input structures, refer to Section 2.3.1.

Table 2-12 Structures

Structure name	Size (bytes)	Outline
XARelrdr	1424 (bytes)	API's structure to stores the information of API
XARelcap	1384 (bytes)	API's structure to stores the information of API

2.3.1 XARelrdr type structure

The XARelrdr type structure is the work area used by the renderer of Renderer plugin. When using this plugin, secure the area with the application program. It's not necessary to refer to this area because it only contains the internal variables and working buffers of the plugin. Make sure not to change the value of this area with the application program.

Table 2-13 XARelrdr type structure information

Member name	Outline
pVOID pMem_tabs	Memory table controller
UWORD32 ring_num	Number of ring buffer
UWORD32 ring_size	Total size of ring-buffer in sample
UWORD32 buffer_size	Total size of ring-buffer in bytes
UWORD32 sample_size	Size of PCM sample
UWORD32 read_idx	FIFO reading position
volatile UWORD32 buf_idx	Index of the current buffer
volatile UWORD32 last_buf_idx	Index of the previous buffer
UWORD32 filled	Number of samples present in the buffer
UWORD32 state	Component state
UWORD32 consumed	Number of samples consumed to framework
XosEvent relrdr_event	Renderer polling event
XosThread relrdr_thread	Renderer polling thread
UWORD32 frame_size	Number of sample in each frame
UWORD32 in_channels	Number of input channels
UWORD32 out_channels	Number of output channels
UWORD32 in_rate	Input sampling rate
UWORD32 out_rate	Output sampling rate
UWORD32 pcm_width	Sample width
UWORD32 stage_flag	Present current stage used in ADMAC
UWORD32 stage_size	Stage memory block size when using DMAC
UWORD32 stage_num	Stage number when using ADMAC
UWORD32 trans_num	Transfer number time when using ADMAC
relren_Device dev[2]	Output device info array after setting param
relren_Enable_Module enable_module	Module list is used
WORD32 volume	Volume value
UWORD32 mix_ctrl	Mix control value
UWORD32 operation_state	Operation state of plugin
SSIU_SSI_MODULE ssi_module	SSI module information
WORD32 first_run	Flag indicating whether the current stream is the first stream
SRC_START_MODE start_mode	Start mode when using SRC

2.3.2 XARelcap type structure

The XARelcap type structure is the work area used by the capture of Renderer plugin. When using this plugin, secure the area with the application program. It's not necessary to refer to this area because it only contains the internal variables and working buffers of the plugin. Make sure not to change the value of this area with the application program.

Table 2-14 XARelcap type structure information

Member name	Outline
pVOID pMem_tabs	Memory table controller
UWORD32 sample_size	Size of PCM sample
UWORD32 state	Component state
UWORD32 transfered	Number of samples have been transferred
XosEvent relcap_event	Capture polling event
XosThread relcap_thread	Capture polling thread
UWORD32 frame_size	Number of sample in each frame
UWORD32 channels	Number of channels
UWORD32 in_rate	Input sampling rate
UWORD32 out_rate	Output sample rate
UWORD32 pcm_width	Sample width
UWORD32 ring_num	Number of ring buffer
UWORD32 stage_flag	Present current stage used in ADMAC
UWORD32 stage_size	Stage memory block size when using DMAC
UWORD32 stage_num	Stage number when using DMAC
UWORD32 trans_num	Transfer number time when using DMAC
UWORD32 ring_size	Total size of ring-buffer in samples
UWORD32 buffer_size	Total size of ring-buffer in bytes
relcap_Device dev[2]	Output device info array after set param
relcap_Enable_module enable_module	Module list is used
WORD32 volume	Volume value
SSIU_SSI_MODULE ssi_module	SSI module information
UWORD32 operation_state	Operation state of plugin
SRC_START_MODE start_mode	Start mode when using SRC
UWORD32 buf_idx	Index of the current buffer

2.4 Memory Specifications

This section describes the memory areas used by this software.

2.4.1 Persistent Area

Table 2-15 Persistent Area Description

Item	Area which always holds values when this software is used. If the user manipulates this area after initialization, the correct execution of this software is not ensured.
Symbol name	- (freely defined by the user)
Size	Obtain the actually required size with 2.2.2.7
Area reservation	The user should reserve this area.
Allocation	This area is included in RAM.
Alignment	Align this area on a 4-byte boundary.

2.4.2 Stack Area

Table 2-16 Stack Area Description

Item	Stack area used by this software
Symbol name	- (freely defined by the user)
Size	Obtain the actually required size with 2.2.2.7
Area reservation	The user should reserve this area. To use this software, reserve a software stack area which exceeds the size above.
Allocation	This area is included in RAM.
Alignment	-

2.4.3 Heap Area

This software does not use a heap area.

2.4.4 Input Buffer

Input buffer only is used in the renderer case.

Table 2-17 Input Buffer Description

Item	Area which stores inputs from this software. The input buffer contains 16-bit/24-bit linear PCM data (hereinafter called PCM data). If the user manipulates this area during rendering processing, the normal execution of the program cannot be ensured.
Symbol name	- (freely defined by the user)
Size	Please secure more than size with 2.2.2.7 (a multiple of 2.2.2.7).
Area reservation	The user should reserve this area. The user can freely use this area after the rendering of one block.
Allocation	This area is included in RAM.
Alignment	Align this area on a 4-byte boundary.

2.4.5 Output Buffer

Output buffer only is used in the capture case.

Table 2-18 Output Buffer Description

Item	Area which stores outputs from this software. The output buffer contains 16-bit/24-bit linear PCM data (hereinafter called PCM data). If the user manipulates this area during rendering processing, the normal execution of the program cannot be ensured.
Symbol name	- (freely defined by the user)
Size	Please secure more than size with 2.2.2.7 (a multiple of 2.2.2.7).
Area reservation	The user should reserve this area. The user can freely use this area after the rendering of one block.
Allocation	This area is included in RAM.
Alignment	Align this area on a 4-byte boundary.

(1) Input/ Output data storage method

Data is input/ output in the formats as shown in Figure 2-4 (consecutive buffers are specified for the channels). The input/output buffer (memory) stores data in 2-byte (16-bit) units. The byte order for accessing the buffer is little endian (see Figure 2-2).




Figure 2-2 PCM 16-bit Data Access (Little Endian Mode)





Figure 2-3 PCM 24-bit Data Access (Little Endian Mode)



Stereo Output Format
Figure 2-4 Output Formats

2.5 Error Processing

This software's functions return the error codes listed in Table 2-20.

2.5.1 Error codes

Below are the error codes for this software.

Table 2-19 Error Codes for Renderer

Error code (32bit)	Value	Description
[1] XA_NO_ERROR	0x00000000	The processing results are normal. The process has terminated normally.
[2] XA_API_FATAL_MEM_ALLOC	0xFFFF8000	Abnormality has occurred, which disables process continuation. An address of API structure was specified at the argument is NULL, the program execution is incorrect. Because it becomes the common API error, please check the correct procedure.
[3] XA_API_FATAL_MEM_ALIGN	0xFFFF8001	Abnormality has occurred, which disables process continuation. An address of API structure was specified at the argument does not 4 byte align. Because it becomes the common API error, please check the correct procedure.
[4] XA_API_FATAL_INVALID_CMD	0xFFFF8002	Abnormality has occurred, which disables process continuation. The command was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[5] XA_API_FATAL_INVALID_CMD_TYPE	0xFFFF8003	Abnormality has occurred, which disables process continuation. The subcommand was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.

[6] XA_RDR_CONFIG_FATAL_STATE	0xFFFF8881	Abnormality has occurred, which disables process continuation. The subcommand was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[7] XA_RDR_CONFIG_FATAL_ERR_MONO_24BIT	0xFFFF8883	It is an error for invalid setting, 24 bit mono channel case does not supported.
[8] XA_RDR_EXEC_FATAL_STATE	0xFFFF9081	Abnormality has occurred, which disables process continuation. The subcommand was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[7] XA_RDR_EXEC_FATAL_INPUT	0xFFFF9082	Abnormality has occurred, which disables process continuation. The input size is not align with sample size. Because it becomes the common API error, please check the correct size of input buffers.
[9] XA_RDR_EXEC_FATAL_INTERNAL	0xFFFF9083	Abnormality has occurred, which disables process continuation. Some of setting becomes incorrect after combination. Because it becomes the common API error, please check the correct parameters.
[10] XA_RDR_EXEC_FATAL_HW	0xFFFF9080	Abnormality has occurred, which disables process continuation. Hardware modules are not available... Because it becomes the common API error, please check the correct parameters and make sure the resource is validity.
[11] XA_RDR_CONFIG_NONFATAL_ERR_PCM_WIDTH	0x00000880	It is an error for renderer specifications out of the range. The PCM width was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)

[12] XA_RDR_CONFIG_NONFATAL_ERR_CHANNELS	0x00000881	It is an error for renderer specifications out of the range. The channel numbers was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[13] XA_RDR_CONFIG_NONFATAL_ERR_SAMPLE_RATE	0x00000882	It is an error for renderer specifications out of the range. The sample rate was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[14] XA_RDR_CONFIG_NONFATAL_ERR_FRAME_SIZE	0x00000883	It is an error for renderer specifications out of the range. The Input buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[15] XA_RDR_CONFIG_NONFATAL_ERR_SOURCE	0x00000884	It is an error for renderer specifications out of the range. The input buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[16] XA_RDR_CONFIG_NONFATAL_ERR_DMACHANNEL	0x00000885	It is an error for renderer specifications out of the range. The input buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[17] XA_RDR_CONFIG_NONFATAL_VOLUME_RATE	0x00000886	It is an error for renderer specification out of range. The volume rate value was specified at the argument does not support.
[18] XA_RDR_CONFIG_NONFATAL_MIX_CONTROL	0x00000887	It is an error for renderer specification out of range. The mix control value was specified at the argument does not support.

[19] XA_RDR_EXEC_FATAL_FORMAT_MISMATCH	0xFFFF9084	It is an error related to the mismatching data format between 2 output streams which are going to mix together. Please make sure these streams have the same format (PCM width, output sampling rate, output channel).
[20] XA_RDR_CONFIG_NONFATAL_OPERATION	0x00000888	It is an error for renderer specification out of range. The setting state was specified at the argument does not support.
[21] XA_RDR_CONFIG_FATAL_RING_NUM	0xFFFF8884	It is an error for renderer specification out of range regarding the total number of ring buffers to be used.
[22]	Others	Reserved

Table 2-20 Error Codes for Capture

Error code (32bit)	Value	Description
[1] XA_NO_ERROR	0x00000000	The processing results are normal. The process has terminated normally.
[2] XA_API_FATAL_MEM_ALLOC	0xFFFF8000	Abnormality has occurred, which disables process continuation. An address of API structure was specified at the argument is NULL, the program execution is incorrect. Because it becomes the common API error, please check the correct procedure.
[3] XA_API_FATAL_MEM_ALIGN	0xFFFF8001	Abnormality has occurred, which disables process continuation. An address of API structure was specified at the argument does not 4 byte align. Because it becomes the common API error, please check the correct procedure.
[4] XA_API_FATAL_INVALID_CMD	0xFFFF8002	Abnormality has occurred, which disables process continuation. The command was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[5] XA_API_FATAL_INVALID_CMD_TYPE	0xFFFF8003	Abnormality has occurred, which disables process continuation. The subcommand was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[6] XA_CAP_CONFIG_FATAL_STATE	0xFFFF88C0	Abnormality has occurred, which disables process continuation. The subcommand was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[7] XA_CAP_CONFIG_FATAL_ERR_MONO_24BIT	0xFFFF88C2	It is an error for invalid setting, 24 bit mono channel case does not supported.

[8] XA_CAP_EXEC_FATAL_STATE	0xFFFF90C0	Abnormality has occurred, which disables process continuation. The subcommand was specified at the argument does not support. Because it becomes the common API error, please check the correct procedure.
[9] XA_CAP_EXEC_FATAL_INTERNAL	0xFFFF90C2	Abnormality has occurred, which disables process continuation. Some of setting becomes incorrect after combination (hardware modules are not available...). Because it becomes the common API error, please check the correct parameters.
[10] XA_CAP_EXEC_FATAL_HW	0xFFFF90C1	Abnormality has occurred, which disables process continuation. Hardware modules are not available... Because it becomes the common API error, please make sure the resource is validity.
[11] XA_CAP_CONFIG_NONFATAL_ERR_PCM_WIDTH	0x000008C0	It is an error for Capture specifications out of the range. The output buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[12] XA_CAP_CONFIG_NONFATAL_ERR_CHANNELS	0x000008C1	It is an error for Capture specifications out of the range. The output buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[13] XA_CAP_CONFIG_NONFATAL_ERR_SAMPLE_RATE	0x000008C2	It is an error for Capture specifications out of the range. The output buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[14] XA_CAP_CONFIG_NONFATAL_ERR_FRAME_SIZE	0x000008C3	It is an error for Capture specifications out of the range. The output buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)

[15] XA_CAP_CONFIG_NONFATAL_ERR_SOURCE	0x000008C4	It is an error for Capture specifications out of the range. The output buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[16] XA_CAP_CONFIG_NONFATAL_ERR_DMACHANNEL	0x000008C5	It is an error for Capture specifications out of the range. The output buffer size was specified at the argument does not support. Please set an appropriate value.(Refer to 2.2.2.16)
[17] XA_CAP_CONFIG_NONFATAL_VOLUME_RATE	0x000008C6	It is an error for Capture specification out of range. The volume rate value was specified at the argument does not support.
[18] XA_CAP_CONFIG_NONFATAL_OPERATION	0x000008C7	It is an error for Capture specification out of range. The setting state was specified at the argument does not support.
[19] XA_CAP_CONFIG_FATAL_RING_NUM	0xFFFF88C4	It is an error for capture specification out of range regarding the total number of ring buffers to be used.
[20]	Others	Reserved

3. Processing Flow

Figure 3-1 shows a flow diagram of processing performed by an application which uses this software. It applies for both case: renderer and capture.

The basic steps executed by the framework are shaded. The steps defined by the user framework are white. Design the process to suit the target system.




Figure 3-1 Example of the Application Processing Flow

4. Appendix

This section will explain more detail about the configuration to using CTU, MIX module to perform channel transfer and mixing functions.

4.1 CTU (Channel transfer unit)

CTU implements the channel transfer unit function. It converts PCM format from "x" channel (for input PCM of Renderer plugin) to "y" channel (expected output channel for speaker).
(*x = monaural, stereo, 4 channels, 6 channels, 8 channels; y = monaural, stereo*)

The setting of input, output channel can be referred in XA_API_CMD_SET_CONFIG_PARAM command.

To use CTU functions, the input channel's and output channel's values must be different, if not, it implies that CTU module is not used, except when Renderer is using MIX function. Because CTU and MIX are electrically connected as Figure 4-1.

There are two discrete CTU modules available. And each module includes four sub-modules. The output of these sub-modules internally connects a MIX module (see Figure 4-1).

So, if you play two PCMs (from 2 Renderers) and mix them together, two sub-modules of CTU0 will be enabled, while CTU1 module is still available. But if you use CTU function in playing two PCMs (from 2 Renderers) separately to two different outputs, then both CTU0 and CTU1 are enabled. Note that, the index of CTU will be selected inside Renderer plugins automatically.

Figure 4-1 shows all available of CTU modules.




Figure 4-1 Block diagram of CTU

4.2 MIX (Mixing)

MIX implements the mixing (adding) two to four streams from Renderer plugins into a single stream, which will be output to a speaker.

The setting of plugin to use MIX functions can be referred to XA_API_CMD_SET_CONFIG_PARAM command.

As Figure 4-1, there are two MIX modules available. And each one supports maximum of 4 inputs.

The below conditions must be assured when mixing PCM's output from Renderers.

- (1) Set mix control flag
 - Plugin has to set the mix control flag to assure that this stream want to mix with others.
- (2) Same output destination
 - All plugins have to set the same output SSI module index. Otherwise, the plugin will play independently as PCM 3 in Figure 4-2.
- (3) Input mixing available
 - A Mix module supports maximum of 4 streams. So when the 5th stream performs mixing (condition (2)), the busy error of hardware will be returned.
- (4) Consistent PCM's format
 - The output PCM format (output channels, output sampling rate, and PCM width) has to have same configurations. Otherwise, this plugin will return an error and stop immediately.

Below are figures that present some use cases in using CTU/MIX modules in ADSP Renderer plugin.




Figure 4-2 Example of using CTU/MIX for 3 streams to SSI0 and another stream to SSI3




Figure 4-3 Example of using CTU/MIX to play 8 streams to SSI0 and SSI3.

About the volume control feature, MIX supports to control the decibel (gain level) of each input stream. From that, the output volume will be controlled by both DVC and MIX (Figure 4-3). On the other hand, by setting MIX, user can set different volume rates for four Renderer plugins when mixing. The output sound is a combination of the inputs and their expected volumes.

4.5 State transformation




Figure 4-5 State transformation in the plugin

Figure above shows how state is transformed in the plugin. When the current state is RESET, the plugin itself changes the state internally to RUN in the next execution.

CONFIDENTIAL

Revision History	ADSP Reference Renderer/Capture Plugin User's Manual
------------------	--

Rev.	Date	Description	
		Page	Summary
1.00	May. 24, 2019	-	New Create

ADSP Reference Renderer/Capture Plugin User's Manual

Publication Date: May 24, 2019 Rev. 1.00

Published by: Renesas Electronics Corporation



SALES OFFICES

Renesas Electronics Corporation

<http://www.renesas.com>

Refer to "<http://www.renesas.com/>" for the latest and detailed information.

Renesas Electronics Corporation

TOYOSU FORESIA, 3-2-24 Toyosu, Koto-ku, Tokyo 135-0061, Japan

Renesas Electronics America Inc.

1001 Murphy Ranch Road, Milpitas, CA 95035, U.S.A.

Tel: +1-408-432-8888, Fax: +1-408-434-5351

Renesas Electronics Canada Limited

9251 Yonge Street, Suite 8309 Richmond Hill, Ontario Canada L4C 9T3

Tel: +1-905-237-2004

Renesas Electronics Europe Limited

Dukes Meadow, Millboard Road, Bourne End, Buckinghamshire, SL8 5FH, U.K

Tel: +44-1628-651-700

Renesas Electronics Europe GmbH

Arcadiastrasse 10, 40472 Düsseldorf, Germany

Tel: +49-211-6503-0, Fax: +49-211-6503-1327

Renesas Electronics (China) Co., Ltd.

Room 1709 Quantum Plaza, No.27 ZhichunLu, Haidian District, Beijing, 100191 P. R. China

Tel: +86-10-8235-1155, Fax: +86-10-8235-7679

Renesas Electronics (Shanghai) Co., Ltd.

Unit 301, Tower A, Central Towers, 555 Langao Road, Putuo District, Shanghai, 200333 P. R. China

Tel: +86-21-2226-0888, Fax: +86-21-2226-0999

Renesas Electronics Hong Kong Limited

Unit 1601-1611, 16/F., Tower 2, Grand Century Place, 193 Prince Edward Road West, Mongkok, Kowloon, Hong Kong

Tel: +852-2265-6688, Fax: +852 2886-9022

Renesas Electronics Taiwan Co., Ltd.

13F, No. 363, Fu Shing North Road, Taipei 10543, Taiwan

Tel: +886-2-8175-9600, Fax: +886 2-8175-9670

Renesas Electronics Singapore Pte. Ltd.

80 Bendemeer Road, Unit #06-02 Hyflux Innovation Centre, Singapore 339949

Tel: +65-6213-0200, Fax: +65-6213-0300

Renesas Electronics Malaysia Sdn.Bhd.

Unit 1207, Block B, Menara Amcorp, Amcorp Trade Centre, No. 18, Jln Persiaran Barat, 46050 Petaling Jaya, Selangor Darul Ehsan, Malaysia

Tel: +60-3-7955-9390, Fax: +60-3-7955-9510

Renesas Electronics India Pvt. Ltd.

No.777C, 100 Feet Road, HAL 2nd Stage, Indiranagar, Bangalore 560 038, India

Tel: +91-80-67208700, Fax: +91-80-67208777

Renesas Electronics Korea Co., Ltd.

17F, KAMCO Yangjae Tower, 262, Gangnam-daero, Gangnam-gu, Seoul, 06265 Korea

Tel: +82-2-558-3737, Fax: +82-2-558-5338



ルネサスエレクトロニクス株式会社

営業お問合せ窓口

<http://www.renesas.com>

営業お問合せ窓口の住所は変更になることがあります。最新情報につきましては、弊社ホームページをご覧ください。

ルネサス エレクトロニクス株式会社 〒135-0061 東京都江東区豊洲3-2-24 (豊洲フォレシア)

技術的なお問合せおよび資料のご請求は下記どうぞ。
総合お問合せ窓口：<https://www.renesas.com/contact/>

ADSP Reference Renderer/Capture Plugin

RCG3AHPLN0203ZDO